


Set Up POP - Outlook® 2007

For increased security, we recommend that you use our secure (SSL) servers, as detailed below. **Note:** If your internal system configurations require non-SSL ports, please see the "[Email Server Settings](#)" page for our full list of available servers and ports.

To set up Outlook 2007 for POP, perform the following steps:

1. In Outlook, select **Tools / Account Settings**.
2. On the **Email** tab, click the **New** button.



3. If prompted, ensure that the **Microsoft Exchange, POP3, IMAP, or HTTP** radio button is selected, and click the **Next** button.
4. Check the **Manually configure server settings or additional server types** box.
5. Click the **Next** button.
6. Ensure that the **Internet E-mail** radio button is selected, and click the **Next** button.
7. Enter the following information:


- Your Name—Enter your first and last name. This is the name that will appear in the **From** field of messages you send.
- E-mail Address—Enter your entire email address (e.g., myname@mydomain.com).
- Account Type—Select **POP3** from the drop-down menu.
- Incoming mail server—Enter the secure server name:

secure.emailsrvr.com

- Outgoing mail server (SMTP)—Enter the secure server name:


secure.emailsrvr.com

- User Name—Enter your entire email address (e.g., myname@mydomain.com).
- Password—Enter the password for your email account.

A screenshot of the Outlook 'User Information' dialog box. It contains the following fields:

- User Information**
 - Your Name: My Name
 - E-mail Address: myname@mydomain.com
- Server Information**
 - Account Type: POP3 (dropdown menu)
 - Incoming mail server: secure.emailsrvr.com
 - Outgoing mail server (SMTP): secure.emailsrvr.com
- Logon Information**
 - User Name: myname@mydomain.com
 - Password: *****
 - Remember password

8. Check the **Remember password** box, if you want Outlook to check for email without prompting you to enter your password.
9. Click the **More Settings** button.
10. Click the **Outgoing Server** tab.
11. Check the **My outgoing server (SMTP) requires authentication** box. Leave the default setting, **Use same settings as my incoming mail server**.




My outgoing server (SMTP) requires authentication

Use same settings as my incoming mail server

Log on using

12. Click the **Advanced** tab.



General | Outgoing Server | Connection | **Advanced**

Server Port Numbers

Incoming server (POP3): 995 Use Defaults

This server requires an encrypted connection (SSL)

Outgoing server (SMTP): 587

Use the following type of encrypted connection: SSL

Server Timeouts

Short ————— Long 1 minute

Delivery

Leave a copy of messages on the server

Remove from server after 10 days

Remove from server when deleted from 'Deleted Items'

13. Check the **This server requires an encrypted connection (SSL)** box.
14. In the **Use the following type of encrypted connection** dropdown menu, select **SSL**.
15. In the **Incoming server (POP3)** box, enter the secure incoming port: **995**
16. In the **Outgoing server (SMTP)** box, enter the secure outgoing port: **587**.
17. A POP connection normally removes the email messages from the server during download. If you would like to leave copies on the server, select the **Leave a copy of messages on server** check box. To avoid exceeding your account's storage limits, indicate whether the server should delete messages after a certain number of days and/or delete messages when you manually delete them from the Deleted Items folder.
18. Click the **OK** button.
19. Click the **Next** button.
20. Click the **Finish** button.
21. Click the **Close** button.